

Display and Modify System Defaults

Enter Code D on the System Defaults menu to display the system defaults of the PAC. A Display System Defaults screen will appear. It differs from a Modify System Defaults screen only in that all its fields except the command line are protected.

Enter Code M on the System Defaults menu to modify the system defaults of the PAC.

A Modify System Defaults screen appears:

```
18:37:52      ***** PREDICT APPLICATION CONTROL *****          2000-04-20
User SAGU           - Modify System Defaults -
Profile .. SYSTEM                         Modified: 1998-11-10 By: SAGU

System Title ..... ***** PREDICT APPLICATION CONTROL *****_
Display Banner Screen ..... Y

ET Maximum ..... 20__
Roll Count ..... 500__

Default Batch User ID ..... *USER__
JCL Substitution Character ... @
Finalize PAC Job Name ..... BS2_BATCH_JCL_____
Maintenance Request Gen No ... 00001

PCF Coordinator FDIC ... Dbnr 164__ ... Fnr 133__

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
Help   Menu  Exit                                Canc
```

The values of its nine unprotected fields are described below:

Value	Description
System Title	The title to appear at the top of the PAC screens.
Display Banner Screen:	NO (N) not to display a banner screen when the PAC is started; YES (Y) to display it.
ET Maximum	The maximum number of held ISNs.
Roll Count	The maximum number of teleprocessing transactions between Natural task rolls (the TP parameter).
Default Batch User ID	@USER substitution parameter Batch user ID User ID batch User ID Natural session User ID to be used when a batch job is submitted. This value is also used for the @USER substitution parameter in batch job JCL. The default will substitute @USER with the user's Natural session user ID (*USER).
JCL Substitution Character	The initial character of the names of JCL substitution parameters.
Finalize PAC Job Name	The name of the JCL text to be used at archiving event finalization unless the finalizer specifies another JCL text or finalizes the event online.
Maintenance Request Gen No	The current maintenance request @GEN replacement.
PCF Coordinator FDIC	Enables you to set / define the Coordinator FDIC for the PAC PCF file.

Modify the displayed values and press ENTER to apply the changes. Press PF3 to return to the System Defaults menu without changing the values of the PAC parameters.